

# HP48GX Installation


Bob Wheeler

Jan 1999

You must move the programs in the file VadeHP to your HP48GX. To do this you will need a serial cable and a software program. Sources for HP calculations and connectivity kits may be obtained from: <http://www.hpcalc.org/buying.html>. Instructions for installing the cable and the software are in the documentation which you will receive. Once the software and cable are installed, you may transfer the programs in the VadeHP folder to your HP48GX.

To download the VadeMecum, start up the *Filer* program, and locate the folder in which you have downloaded the program files. Select all program files in this folder and send them to your HP48GX: be careful that you do not attempt to send files such as the present document whose file name has the extension .pdf – HP files have no extensions. When the files have been downloaded to your HP48GX, you should run the *setup* program on your HP48GX. Simply type *setup* into the command line and hit the Enter key, or use the *NXT* key to cycle the menu bar till *setup* is found and then press the white key below it. A custom menu will be set up allowing you to access all the VadeMecum functions.

The menu bar produced in the custom setting is shown in the following screen captures:



If you have any questions about whether or not the downloaded programs are correct, you can examine their checksums which are given in the table at the end of the program documentation. To obtain a checksum, put the name of a program on the stack, 'DOFU' for example, then press left arrow, memory, BYTES. The checksum will appear.